Configure Mac Entourage email

In order to send and receive E-mail through your website hosted with FastWebEngine, you can configure Entourage for Mac OS X as your E-mail client with the following required settings. This step-by-step tutorial will demonstrate how to make the necessary changes so that you will be sending and receiving E-mail quickly and conveniently.
Start by configuring Entourage with your new E-mail account so that Entourage will check E-mail services hosted by FastWebEngine (The following steps bypass the Setup Assistant) - Let's begin:

Step 1:

With Entourage open, click on the **Tools** menu at the top of the screen and then click on **Accounts**.



Step 2:

When the **Accounts** window opens, click the **New** button in the upper-left corner of the window and select **Mail**.



Step 3:

When the **Account Setup Assistant** box appears select the **Configure account manually** button at the bottom of the window.

Step 4:

When the **New Account** box appears select either **POP** or **IMAP** for your server type. If you are not certain which one to select, **POP** is the most common setting. Click **OK**.



Step 5:

The **Edit Account** box will now appears - this is where you will configure the bulk of your account settings. In this window you will enter the following information:

- **Account Name**: Enter a description for the e-mail account you will be using
- **Name**: Enter your full name
- **Email Address**: Enter the E-mail address that has been configured with FastWebEngine
- **Account ID**: Enter your **FULL E-mail Address** - this is your username to log into the mail server (also used with Webmail)
- **POP Server**: Enter your incoming mail server - **typically mail.yourdomainname.xyz** (.com, .net, .org etc.) - Remember to change the "yourdomainname" to the domain that you are hosting with FastWebEngine
- **Password**: Enter the password for the E-mail address that you are configuring
- **SMTP Server**: Enter your outgoing mail server - **typically mail.yourdomainname.xyz** (.com, .net, .org etc.) - Remember to change the "yourdomainname" to the domain that you are hosting with FastWebEngine

Click **OK** in the Edit Account window.

Close the Accounts window to save your settings.

Step 6 - We're Finished:

You should now be able to send and receive E-mail using your account hosted with FastWebEngine.